

Orders: orders@novusbio.com

Support: technical@novusbio.com

Web: www.novusbio.com

# NBP1-97311 Protocol

Protocols, Publications, Related Products, Reviews and more:

www.novusbio.com/NBP1-97311

# Serum protocol for TRPM8 Antibody (NBP1-97311)

TRPM8 Antibody: https://www.novusbio.com/products/trpm8-antibody\_nbp1-97311 Western Blot Protocol

- 1. Perform SDS-PAGE on samples to be analyzed, loading 40 ug of total protein per lane.
- 2. Transfer proteins to membrane according to the instructions provided by the manufacturer of the membrane and transfer apparatus.
- 3. Stain according to standard Ponceau S procedure (or similar product) to assess transfer success, and mark molecular weight standards where appropriate.
- 4. Rinse the blot.
- 5. Block the membrane using standard blocking buffer for at least 1 hour.
- 6. Wash the membrane in wash buffer three times for 10 minutes each.
- 7. Dilute primary antibody in blocking buffer and incubate 1 hour at room temperature.
- 8. Wash the membrane in wash buffer three times for 10 minutes each.
- 9. Apply the diluted HRP conjugated secondary antibody in blocking buffer (as per manufacturers instructions) and incubate 1 hour at room temperature.
- 10. Wash the blot in wash buffer three times for 10 minutes each (this step can be repeated as required to reduce background).
- 11. Apply the detection reagent of choice in accordance with the manufacturers instructions.

Note: Tween-20 can be added to the blocking or antibody dilution buffer at a final concentration of 0.05-0.2%.

# Immunohistochemistry-Paraffin Embedded Sections

#### Antigen Unmasking:

Bring slides to a boil in 10 mM sodium citrate buffer (pH 6.0) then maintain at a sub-boiling temperature for 10 minutes. Cool slides on bench-top for 30 minutes.

## Staining:

- 1. Wash sections in deionized water three times for 5 minutes each.
- 2. Wash sections in wash buffer for 5 minutes.
- 3. Block each section with 100-400 ul blocking solution for 1 hour at room temperature.
- 4. Remove blocking solution and add 100-400 ul diluted primary antibody. Incubate overnight at 4 C.
- 5. Remove antibody solution and wash sections in wash buffer three times for 5 minutes each.
- 6. Add 100-400 ul biotinylated diluted secondary antibody. Incubate 30 minutes at room temperature.
- 7. Remove secondary antibody solution and wash sections three times with wash buffer for 5 minutes each.
- 8. Add 100-400 ul Streptavidin-HRP reagent to each section and incubate for 30 minutes at room temperature.
- 9. Wash sections three times in wash buffer for 5 minutes each.
- 10. Add 100-400 ul DAB substrate to each section and monitor staining closely.
- 11. As soon as the sections develop, immerse slides in deionized water.
- 12. Counterstain sections in hematoxylin.
- 13. Wash sections in deionized water two times for 5 minutes each.
- 14. Dehydrate sections.
- 15. Mount coverslips.

## Immunocytochemistry Protocol

Culture cells to appropriate density in 35 mm culture dishes or 6-well plates.

- 1. Remove culture medium and add 10% formalin to the dish. Fix at room temperature for 30 minutes.
- 2. Remove the formalin and add ice cold methanol. Incubate for 5-10 minutes.
- 3. Remove methanol and add washing solution (i.e. PBS). Be sure to not let the specimen dry out. Wash three times for 10 minutes.
- 4. To block nonspecific antibody binding incubate in 10% normal goat serum from 1 hour to overnight at room

temperature.

- 5. Add primary antibody at appropriate dilution and incubate at room temperature from 2 hours to overnight at room temperature.
- 6. Remove primary antibody and replace with washing solution. Wash three times for 10 minutes.
- 7. Add secondary antibody at appropriate dilution. Incubate for 1 hour at room temperature.
- 8. Remove antibody and replace with wash solution, then wash for 10 minutes. Add Hoechst 33258 to wash solution at 1:25,0000 and incubate for 10 minutes. Wash a third time for 10 minutes.
- 9. Cells can be viewed directly after washing. The plates can also be stored in PBS containing Azide covered in Parafilm (TM). Cells can also be cover-slipped using Fluoromount, with appropriate sealing.

\*The above information is only intended as a guide. The researcher should determine what protocol best meets their needs. Please follow safe laboratory procedures.